

# Wireless LAN Setup Manual

## — Mac OS 10.3～ —

Computing and Networking Center  
<http://www.cc.u-ryukyu.ac.jp>  
[admin@cc.u-ryukyu.ac.jp](mailto:admin@cc.u-ryukyu.ac.jp)

## Wireless LAN Setup Manual (Mac OS 10.3～)


### 1.Setup of Network




Click this icon and open the System environment settings.  
The icon is in the dock bottom of screen.



Click the “ネットワーク”



Double click the “AirMac”



Click the “TCP/IP” tab and chose “DHCP サーバを参照” from “IPv4 を設定”

Click the “今すぐ適用” and close this screen.

## 2. Setup of “AirMac”




Click “AirMac ステータスアイコン” and open “インターネット接続”



Check “802.1X” in red line.

\* It is not at there usually so you must setup by follow way.

## 2.1. Add “802.1X”



Click “新規 802.1X 接続”




Check the icon which in there or not.



Click “802.1X” and Click triangle of “設定”




Click the “設定を編集”



Check only “TTLS” and Click “設定”



Chose “PAP” from “TTLS 内部認証”  
Click the “OK”



Click the “OK”

### 3. 無線 LAN の接続



Chose wireless network like “ryukyu-ap～”  
And click “接続”



Input your userID and password which are issued by Computing and Networking Center and click “OK”



Click “すべてに同意する”



Input your userID and password again.  
Click “OK”

”



If you have a message as “TTLS 経由で接続しました”, you succeeded to connect.

#### 4. How to connect after next time



Click “Air Mac ステータスアイコン” from menu bar and chose “該当するワイヤレスネットワークを選択”  
※ Wireless network is like ”ryukyu-ap\*\*\*-\*\*\*”



Input your userID and password and click “OK”

If you have a question about Wireless LAN, please call 8 9 4 7  
<http://www.cc.u-ryukyu.ac.jp>  
[admin@cc.u-ryukyu.ac.jp](mailto:admin@cc.u-ryukyu.ac.jp)